

Description

RF Creditor Reference contains 25 characters in alphanumeric string and can be used when assigning and identifying unique identifiers.

Many countries have their own country-specific standards for identifiers. Purpose of RF Creditor Reference is to offer a standard which can be used instead of a country specific identifier. This increases STP process, especially when an identifier must cross national borders.

Other names and background

RF Creditor Reference is based on ISO 11649. Names for this standard in various implementation guides include:

- RF Creditor Reference
- ISO 11649 Reference
- ISO Reference
- RF Reference
- Structured Creditor Reference


Standard was implemented at the end of 2008, first seen in SEPA rulebook 3.2.

Usage

Messages where Creditor Reference may be used in various payments related messages, including invoices, credit transfers direct debits.

Format

Reference always contains maximum of 25 characters. Positions 1-2 contain identifier "RF" (separating this reference from the myriad of others), positions 3-4 contain check digit and positions onwards may contain alphanumeric characters, forming the actual reference. Alphanumeric characters allowed are digits and upper&lower letters from A to Z.



Purpose of check digit is to confirm that manually input reference is correct.

Check digit algorithm

In the reference section of RF, letters are converted into numbers and mod-97 (used in IBAN check digit

calculation as well) operation is done to the reference in a numeric format. Result of this calculation will have to match the check digits indicated in position 3-4.

In order to convert the reference string into integers, letters must be converted using the following logic:

A/a = 10, B/b = 11, ..., Z/z = 35